

# Vivante programming: DPU API reference guide

*Note:* **The current release supports DPU API version 3.0.**

## About this document

### Scope and purpose

This document describes various Display Processor Unit (DPU) APIs available for the user to make use of Display Controller.

### Intended audience

This document is intended for anyone who wants to make use of the DPU API for performing Display Controller operations.

## Table of contents

## Table of contents

<b>About this document.....</b>	<b>1</b>
<b>Table of contents.....</b>	<b>2</b>
<b>1 Overview.....</b>	<b>4</b>
1.1 Compatibility.....	4
1.2 API files .....	4
<b>2 Data structures .....</b>	<b>5</b>
2.1 Value types .....	5
2.2 Pointer types .....	6
2.3 Enumerations .....	7
2.3.1 vivSTATUS .....	7
2.3.2 viv_input_format_type .....	7
2.3.3 viv_tiling_type.....	10
2.3.4 viv_display_type .....	11
2.3.5 viv_dbi_type.....	11
2.3.6 viv_display_format_type .....	11
2.3.7 viv_filter_tap_type.....	13
2.3.8 viv_cursor_size_type .....	13
2.3.9 viv_alpha_mode.....	13
2.3.10 viv_cache_mode .....	13
2.3.11 viv_global_alpha_mode .....	14
2.3.12 viv_porter_duff_mode.....	14
2.3.13 viv_pool_type.....	15
2.3.14 viv_display_size_type .....	15
2.3.15 viv_display.....	16
2.3.16 viv_dc_features.....	16
2.3.17 viv_dc_layer_cap .....	17
2.4 Structures .....	17
2.4.1 viv_dc_buffer.....	17
2.4.2 3.5.2 viv_set_cursor()viv_tilestatus_buffer .....	18
2.4.3 viv_cursor .....	19
2.4.4 viv_layer_alpha_mode .....	20
2.4.5 viv_dc_degama.....	20
2.4.6 viv_dc_gamma .....	20
2.4.7 viv_output .....	20
2.4.8 viv_dc_rect .....	21
2.4.9 viv_dc_color .....	21
<b>3 DPU APIs .....</b>	<b>22</b>
3.1 Initialization.....	22
3.1.1 viv_dc_init().....	22
3.1.2 viv_dc_deinit().....	23
3.1.3 viv_dc_reset() .....	23
3.2 Buffer allocation.....	24
3.2.1 viv_alloc_buffer() .....	24
3.2.2 viv_free_buffer() .....	25
3.3 Capability query .....	26
3.3.1 viv_query_chipinfo() .....	26
3.3.2 viv_dc_query_feature().....	27

## Table of contents

3.3.3	viv_layer_query_capability() .....	28
3.4	Overlay and video/graphic layers .....	28
3.4.1	viv_dc_select_layer() .....	28
3.4.2	viv_layer_enable() .....	29
3.4.3	viv_layer_set() .....	30
3.4.4	viv_layer_zorder() .....	31
3.4.5	viv_layer_set_position() .....	32
3.4.6	viv_layer_colorkey() .....	33
3.4.7	viv_layer_clear() .....	34
3.4.8	viv_set_alpha() .....	35
3.4.9	viv_layer_poterduff_blend() .....	35
3.4.10	viv_layer_set_watermark() .....	36
3.4.11	viv_dc_set_qos() .....	36
3.4.12	viv_layer_set_display() .....	37
3.5	Background and cursor layers .....	37
3.5.1	viv_layer_set_background() .....	37
3.5.2	viv_set_cursor() .....	38
3.5.3	viv_cursor_security() .....	39
3.5.4	viv_cursor_offset() .....	40
3.5.5	viv_cursor_move() .....	41
3.6	Post-processing for display .....	42
3.6.1	viv_gamma_enable() .....	42
3.6.2	viv_gamma_init() .....	43
3.6.3	viv_set_gamma() .....	44
3.6.4	viv_set_dither() .....	45
3.7	Display output .....	46
3.7.1	viv_set_display_size() .....	46
3.7.2	viv_set_custom_display_size() .....	47
3.7.3	viv_set_output() .....	48
3.7.4	viv_reset_dbi() .....	49
3.7.5	viv_set_output_dbi() .....	49
3.8	Display controller access and debugging .....	50
3.8.1	viv_set_commit() .....	50
3.8.2	viv_get_vblank_count() .....	51
<b>4</b>	<b>Programming with DPU APIs .....</b>	<b>52</b>
4.1	Example 1: Displaying through DPI .....	53
4.2	Example 2: Displaying through DBI Type B .....	55
<b>5</b>	<b>List of Unsupported DPU APIs .....</b>	<b>57</b>
	<b>Revision history .....</b>	<b>58</b>
	<b>Disclaimer .....</b>	<b>59</b>

## 1 Overview

### 1 Overview

The DPU API set serves to develop user applications to control Vivante display controllers of the newest architecture. For the supported display controllers, see Section [1.1, Compatibility](#).

This document describes the APIs, and the data structures used in the DPU API set. It also outlines the procedure of programming with this API set.

- Chapter [2, Data structures](#)
- Chapter [3, DPU APIs](#)
- Chapter [4, Programming with DPU APIs](#)

#### 1.1 Compatibility

This API set is compatible with the DC8000Nano Vivante display controller.

#### 1.2 API files

The definition files for data structures and APIs are:

- Types and enumerations:

*viv\_dc\_type.h*

- APIs:

*viv\_dc\_setting.h*

## 2 Data structures

## 2 Data structures

### 2.1 Value types

The following table lists the value types defined in the DPU API set.

**Table 1** Value types

Name	Definition	Description
gctBOOL	int	A Boolean value <ul style="list-style-type: none"> <li>0: SET_DISABLE, SET_NEGATIVE, vivFALSE, or gcvFALSE</li> <li>1: SET_ENABLE, SET_POSITIVE, vivTRUE, or gcvTRUE</li> </ul>
gctCHAR	char	An 8-bit character value
gctFLOAT	float	A single-precision floating-point number
gctINT	int	A signed integer
gctINT8	signed char	A signed 8-bit integer
gctINT16	signed short	A signed 16-bit integer
gctINT32	signed int	A signed 32-bit integer
gctINT64	signed long long	A signed 64-bit integer
gctSIZE_T	unsigned long	An unsigned 64-bit integer
gctUINT	unsigned int	An unsigned integer
gctUINT8	unsigned char	An unsigned 8-bit integer
gctUINT16	unsigned short	An unsigned 16-bit integer
gctUINT32	unsigned int	An unsigned 32-bit integer
gctUINT64	unsigned long long	An unsigned 64-bit integer
gctVOID	void	Void
gctDOUBLE	double	A double-precision floating-point number

## 2 Data structures

### 2.2 Pointer types

The following table lists the pointer types defined in the DPU API set. For the referent data types, see section 2.1, [Value types](#).

**Table 2** Pointer types

Pointer type	Name	Description
<code>gctBOOL *</code>	<code>gctBOOL_PTR</code>	A pointer to a Boolean value
<code>void *</code>	<code>gctFILE</code>	A pointer to a file
<code>float *</code>	<code>gctFLOAT_PTR</code>	A pointer to a single-precision floating-point number
<code>void *</code>	<code>gctHANDLE</code>	A handle of the operating system
<code>gctINT *</code>	<code>gctINT_PTR</code>	A pointer to a signed integer
<code>gctINT8 *</code>	<code>gctINT8_PTR</code>	A pointer to a signed 8-bit integer
<code>gctINT16 *</code>	<code>gctINT16_PTR</code>	A pointer to a signed 16-bit integer
<code>gctINT32 *</code>	<code>gctINT32_PTR</code>	A pointer to a signed 32-bit integer
<code>gctINT64 *</code>	<code>gctINT64_PTR</code>	A pointer to a signed 64-bit integer
<code>void *</code>	<code>gctPHYS_ADDR</code>	A pointer to a physical address
<code>void *</code>	<code>gctPOINTER</code>	A generic pointer
<code>gctSIZE_T *</code>	<code>gctSIZE_T_PTR</code>	A pointer to an unsigned 64-bit integer
<code>void *</code>	<code>gctSTRING</code>	A pointer to a string
<code>gctUINT *</code>	<code>gctUINT_PTR</code>	A pointer to an unsigned integer
<code>gctUINT8 *</code>	<code>gctUINT8_PTR</code>	A pointer to an unsigned 8-bit integer
<code>gctUINT16 *</code>	<code>gctUINT16_PTR</code>	A pointer to an unsigned 16-bit integer
<code>gctUINT32 *</code>	<code>gctUINT32_PTR</code>	A pointer to an unsigned 32-bit integer
<code>gctUINT64 *</code>	<code>gctUINT64_PTR</code>	A pointer to an unsigned 64-bit integer

## 2 Data structures

### 2.3 Enumerations

#### 2.3.1 vivSTATUS

Specifies the return code of a DPU API.

Enumeration value	Numeric value	Description
vivSTATUS_HEAP_CORRUPTED	-7	Heap corrupted
vivSTATUS_OUT_OF_RESOURCES	-6	Resource access out of bounds
vivSTATUS_TIMEOUT	-5	Timeout
vivSTATUS_NOT_SUPPORT	-4	Unsupported features
vivSTATUS_OOM	-3	Out of memory
vivSTATUS_FAILED	-2	File operation failed
vivSTATUS_INVALID_ARGUMENTS	-1	Invalid input parameters
vivSTATUS_OK	0	Function successful

#### 2.3.2 viv\_input\_format\_type

Specifies the color format of the input.

##### RGB formats

*Note:* The display controller does not support 24 bpp RGB formats for DC8000Nano.

Enumeration value	Description
vivARGB4444	16-bit ARGB format with the alpha channel in bits 15:12, the red channel in bits 11:8, the green channel in bits 7:4, and the blue channel in bits 3:0
vivABGR4444	16-bit ABGR format with the alpha channel in bits 15:12, the blue channel in bits 11:8, the green channel in bits 7:4, and the red channel in bits 3:0
vivRGBA4444	16-bit RGBA format with the red channel in bits 15:12, the green channel in bits 11:8, the blue channel in bits 7:4, and the alpha channel in bits 3:0
vivBGRA4444	16-bit BGRA format with the blue channel in bits 15:12, the green channel in bits 11:8, the red channel in bits 7:4, and the alpha channel in bits 3:0
vivXRGB4444	16-bit XRGB format with the X channel in bits 15:12, the red channel in bits 11:8, the green channel in bits 7:4, and the blue channel in bits 3:0
vivXBGR4444	16-bit XBGR format with the X channel in bits 15:12, the blue channel in bits 11:8, the green channel in bits 7:4, and the red channel in bits 3:0
vivRGBX4444	16-bit RGBX format with the red channel in bits 15:12, the green channel in bits 11:8, the blue channel in bits 7:4, and the X channel in bits 3:0
vivBGRX4444	16-bit BGRX format with the blue channel in bits 15:12, the green channel in bits 11:8, the red channel in bits 7:4, and the X channel in bits 3:0
vivARGB1555	16-bit ARGB format with the alpha channel in bit 15, the red channel in bits 14:10, the green channel in bits 9:5, and the blue channel in bits 4:0
vivABGR1555	16-bit ABGR format with the alpha channel in bit 15, the blue channel in bits 14:10, the green channel in bits 9:5, and the red channel in bits 4:0

## 2 Data structures

Enumeration value	Description
vivRGBA1555	16-bit RGBA format with the red channel in bits 15:11, the green channel in bits 10:6, the blue channel in bits 5:1, and the alpha channel in bit 0
vivBGRA1555	16-bit BGRA format with the blue channel in bits 15:11, the green channel in bits 10:6, the red channel in bits 5:1, and the alpha channel in bit 0
vivXRGB1555	16-bit XRGB format with the X channel in bit 15, the red channel in bits 14:10, the green channel in bits 9:5, and the blue channel in bits 4:0
vivXBGR1555	16-bit XBGR format with the X channel in bit 15, the blue channel in bits 14:10, the green channel in bits 9:5, and the red channel in bits 4:0
vivRGBX1555	16-bit RGBX format with the red channel in bits 15:11, the green channel in bits 10:6, the blue channel in bits 5:1, and the X channel in bit 0
vivBGRX1555	16-bit BGRX format with the blue channel in bits 15:11, the green channel in bits 10:6, the red channel in bits 5:1, and the X channel in bit 0
vivRGB565	16-bit RGB format with the red channel in bits 15:11, the green channel in bits 10:5, and the blue channel in bits 4:0
vivBGR565	16-bit BGR format with the blue channel in bits 15:11, the green channel in bits 10:5, and the red channel in bits 4:0
vivARGB8888	32-bit ARGB format with the alpha channel in bits 31:24, the red channel in bits 23:16, the green channel in bits 15:8, and the blue channel in bits 7:0
vivABGR8888	32-bit ABGR format with the alpha channel in bits 31:24, the blue channel in bits 23:16, the green channel in bits 15:8, and the red channel in bits 7:0
vivRGBA8888	32-bit RGBA format with the red channel in bits 31:24, the green channel in bits 23:16, the blue channel in bits 15:8, and the alpha channel in bits 7:0
vivBGRA8888	32-bit BGRA format with the blue channel in bits 31:24, the green channel in bits 23:16, the red channel in bits 15:8, and the alpha channel in bits 7:0
vivXRGB8888	32-bit XRGB format with the X channel in bits 31:24, the red channel in bits 23:16, the green channel in bits 15:8, and the blue channel in bits 7:0
vivXBGR8888	32-bit XBGR format with the X channel in bits 31:24, the blue channel in bits 23:16, the green channel in bits 15:8, and the red channel in bits 7:0
vivRGBX8888	32-bit RGBX format with the red channel in bits 31:24, the green channel in bits 23:16, the blue channel in bits 15:8, and the X channel in bits 7:0
vivBGRX8888	32-bit BGRX format with the blue channel in bits 31:24, the green channel in bits 23:16, the red channel in bits 15:8, and the X channel in bits 7:0
vivARGB2101010	32-bit ARGB2101010 format with the alpha channel in bits 31:30, the red channel in bits 29:20, the green channel in bits 19:10, and the blue channel in bits 9:0
vivCURSOR_ARGB	The ARGB8888 format, which is supported for the cursor. For details about this format, see the description of <a href="#">vivARGB8888</a> .

### YUV formats

Enumeration value	Description
vivYUY2	Packed YUV422 format, 32 bits for 2 pixels, with Y0 in bits 31:24, U0 in bits 23:16, Y1 in bits 15:8, and V0 in bits 7:0.
vivUYVY	Packed YUV422 format, 32 bits for 2 pixels, with U0 in bits 31:24, Y0 in bits 23:16, V0 in bits 15:8, and Y1 in bits 7:0.



## 2 Data structures

Enumeration value	Description
vivNV16	YUV422 semi-planar format with 8 bits occupied by the Y plane and 16 bits occupied by the UV plane per pixel.
vivNV12	YUV420 semi-planar format, also named NV12, with an 8-bit Y plane in one pixel placed before each 16-bit array of packed U (Cb) and V (Cr) planes. The stride of the V and U planes is the same as that of the Y plane, but a V or U plane contains half of the lines in a Y plane.
vivYV12	YUV420 planar format with 8 bits occupied by the Y plane, 8 bits occupied by the U plane, and 8 bits occupied by the V plane per pixel.
vivP010	YUV420 semi-planar format. The Y plane occupies 16 bits per pixel but uses only 10 bits. The UV plane occupies 32 bits per pixel but uses only 20 bits.
vivNV12_10BIT	YUV420 semi-planar format, also named NV12, with a 10-bit Y plane in one pixel placed before each 20-bit array of packed U (Cb) and V (Cr) planes. Four Y-plane pixels occupy 5 bytes. The stride of the V and U planes is the same as that of the Y plane, but a V or U plane contains half of the lines in a Y plane. Only special DC8200 IPs support this format.
vivYUV444	YUV444 planar format with 8 bits occupied by the Y plane, 8 bits occupied by the U plane, and 8 bits occupied by the V plane per pixel. Only special DC8200 IPs support this format.
vivYUV444_10BIT	YUV444 planar format with 10 bits occupied by the Y plane, 10 bits occupied by the U plane, and 10 bits occupied by the V plane per pixel. Four Y-plane pixels occupy 5 bytes. Only special DC8200 IPs support this format.

## 2 Data structures

### 2.3.3 viv\_tiling\_type

Specifies the tiling type.

Enumeration value	Description
vivLINEAR	Linear
vivTILED4X4 <sup>1</sup>	Tile 4x4
vivTILED8X8 <sup>1</sup>	Tile 8x8
vivSUPERTILEDX <sup>1</sup>	SupertileX 8x8 or 8x4
vivSUPERTILEDY <sup>1</sup>	SupertileY 4x8

- Valid only for layers that support tiling. DC8000Nano supports tiling feature, to check [viv\\_layer\\_query\\_capability\(\)](#) can be called with vivLAYER\_CAP\_TILED as an argument.

The following table lists the tiling types supported for each input color format.

*Note: Each RGB color format listed includes their variants with the same channel bitwidth and different channel orders.*

Color format	Linear	Tile 4x4	Tile 8x8	SupertileX	SupertileY
vivARGB8888	Supported			8x4 Supported	Supported
vivXRGB8888	Supported			8x4 Supported	Supported
vivARGB2101010	Supported			8x4 Supported	Supported
vivRGB565	Supported			8x8 Supported	
vivARGB1555	Supported			8x8 Supported	
vivXRGB1555	Supported			8x8 Supported	
vivARGB4444	Supported			8x8 Supported	
vivXRGB4444	Supported			8x8 Supported	
vivYUY2	Supported		Supported		
vivUYVY	Supported		Supported		
vivNV12	Supported	Supported	Supported		
vivP010	Supported		Supported		
vivNV16	Supported				
vivYV12	Supported				
vivNV12_10BIT		Supported			
vivYUV444		Supported			
vivYUV444_10BIT		Supported			

## 2 Data structures

### 2.3.4 viv\_display\_type

Specifies the output interface type.

To query whether an output interface is supported, call [viv\\_dc\\_query\\_feature\(\)](#).

Enumeration value	Description	Supported (Yes/No/Not Applicable)
vivDPI	The Display Pixel Interface (DPI)	Yes
vivDP	The DisplayPort (DP)	No
vivEDP	Reserved	Not Applicable
vivDBI	The Display Bus Interface (DBI)	Yes

### 2.3.5 viv\_dbi\_type

Specifies the type of the Display Bus Interface (DBI).

This enumeration is valid only for display controllers that support DBI output. To query whether DBI output is supported, call the [viv\\_dc\\_query\\_feature\(\)](#) API with vivFEATURE\_DBI.

Enumeration value	Description
vivDBI_AFIXED	Type A Fixed E mode
vivDBI_ACLOCK	Type A Clocked E mode
vivDBI_B	Type B
vivDBI_C	Type C

### 2.3.6 viv\_display\_format\_type

Specifies the color format of the display controller output.

#### DPI output

The following table lists the color formats supported for DPI output.

Enumeration value	Description
vivD24	RGB888
vivD30	RGB101010
vivD16CFG1	RGB565, config 1
vivD16CFG2	RGB565, config 2
vivD16CFG3	RGB565, config 3
vivD18CFG1	RGB666, config 1
vivD18CFG2	RGB666, config 2

#### DP RGB output

The following table lists the color formats supported for DP RGB output.

Enumeration value	Description
vivDPRGB565	RGB565

## 2 Data structures

vivDPRGB666	RGB666
vivDPRGB888	RGB888
vivDPRGB101010	RGB101010

### DP YUV output

The following table lists the color formats supported for DP YUV output.

Enumeration value	Description
vivDPYUV420B8CFG1	8-bit YUV420, config 1
vivDPYUV420B8CFG2	8-bit YUV420, config 2
vivDPYUV420B8CFG3	8-bit YUV420, config 3
vivDPYUV422B8CFG1	8-bit YUV422, config 1
vivDPYUV422B8CFG2	8-bit YUV422, config 2
vivDPYUV444B8CFG1	8-bit YUV444, config 1
vivDPYUV444B8CFG2	8-bit YUV444, config 2
vivDPYUV444B8CFG3	8-bit YUV444, config 3
vivDPYUV420B10CFG1	10-bit YUV420 , config 1
vivDPYUV420B10CFG2	10-bit YUV420, config 2
vivDPYUV420B10CFG3	10-bit YUV420, config 3
vivDPYUV422B10CFG1	10-bit YUV422, config 1
vivDPYUV422B10CFG2	10-bit YUV422, config 2
vivDPYUV444B10CFG1	10-bit YUV444, config 1
vivDPYUV444B10CFG2	10-bit YUV444, config 2
vivDPYUV444B10CFG3	10-bit YUV444, config 3

### DBI output

The following table lists the color formats supported for DBI output. To query whether DBI output is supported, call [viv\\_dc\\_query\\_feature\(\)](#) with vivFEATURE\_DBI.

Enumeration value	Description
vivD8R3G3B2	D8R3G3B2 for DBI type A and type B
vivD8R4G4B4	D8R4G4B4 for DBI type A and type B
vivD8R5G6B5	D8R5G6B5 for DBI type A and type B
vivD8R6G6B6	D8R6G6B6 for DBI type A and type B
vivD8R8G8B8	D8R8G8B8 for DBI type A and type B
vivD9R6G6B6	D9R6G6B6 for DBI type A and type B
vivD16R3G3B2	D16R3G3B2 for DBI type A and type B
vivD16R4G4B4	D16R4G4B4 for DBI type A and type B
vivD16R5G6B5	D16R5G6B5 for DBI type A and type B
vivD16R6G6B6OP1	D16R6G6B6 option 1 for DBI type A and type B
vivD16R6G6B6OP2	D16R6G6B6 option 2 for DBI type A and type B

## 2 Data structures

vivD16R8G8B8OP1	D16R8G8B8 option 1 for DBI type A and type B
vivD16R8G8B8OP2	D16R8G8B8 option 2 for DBI type A and type B
vivD1R5G6B5OP1	D1R5G6B5 option 1 for DBI type C
vivD1R5G6B5OP2	D1R5G6B5 option 2 for DBI type C
vivD1R5G6B5OP3	D1R5G6B5 option 3 for DBI type C
vivD1R8G8B8OP1	D1R8G8B8 option 1 for DBI type C
vivD1R8G8B8OP2	D1R8G8B8 option 2 for DBI type C
vivD1R8G8B8OP3	D1R8G8B8 option 3 for DBI type C

### 2.3.7 viv\_filter\_tap\_type

Specifies the filter tap type.

In the following table, filter tap patterns are described in [horizontal tap count] x [vertical tap count] format.

Enumeration value	Description
vivFILTER_H3_V3	The filter with 3 x 3 taps
vivFILTER_H5_V3	The filter with 5 x 3 taps

### 2.3.8 viv\_cursor\_size\_type

Specifies the cursor size.

Enumeration value	Description
vivCURSOR_32x32	32 x 32 pixels.
vivCURSOR_64x64	64 x 64 pixels. This value is valid only if the cursor version is 1. To query the cursor version, call <a href="#">viv_dc_query_feature()</a> with vivFEATURE_CURSOR_VERSION.

### 2.3.9 viv\_alpha\_mode

Specifies whether to reverse the alpha value.

Enumeration value	Description
vivALPHA_NORMAL	Does not reverse the alpha value.
vivALPHA_INVERSED	Reverses the alpha value.

### 2.3.10 viv\_cache\_mode

Specifies the cache mode.

Enumeration value	Description
vivCACHE_NONE	No cache configured
vivCACHE_128	128 bytes
vivCACHE_256	256 bytes

## 2 Data structures

### 2.3.11 viv\_global\_alpha\_mode

Specifies the type of alpha value.

Enumeration value	Description
vivGALPHA_NORMAL	Pixel alpha values are used.
vivGALPHA_GLOBAL	The global alpha value is used.
vivGALPHA_SCALED	The used alpha value is scaled from pixel alpha values and the global alpha value.

### 2.3.12 viv\_porter\_duff\_mode

Specifies the Porter-Duff blend mode.

In the following table, Sa indicates the source alpha value, Da indicates the destination alpha value, Sc indicates the source color value, and Dc indicates the destination color value.

Enumeration value	Description
vivPD_CLEAR	Clears destination pixels covered by the source to 0. <ul style="list-style-type: none"> <li>Result alpha value = 0</li> <li>Result color value = 0</li> </ul>
vivPD_SRC	Replaces the destination pixels with the source pixels. <ul style="list-style-type: none"> <li>Result alpha value = Sa</li> <li>Result color value = Sc</li> </ul>
vivPD_DST	Discards the source pixels and leaves the destination unchanged. <ul style="list-style-type: none"> <li>Result alpha value = Da</li> <li>Result color value = Dc</li> </ul>
vivPD_SRC_OVER	Draws the source pixels over the destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>Sa + (1 - Sa) \times Da</math></li> <li>Result color value = <math>Sc + (1 - Sa) \times Dc</math></li> </ul>
vivPD_DST_OVER	Draws the source pixels behind the destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>Da + (1 - Da) \times Sa</math></li> <li>Result color value = <math>Dc + (1 - Da) \times Sc</math></li> </ul>
vivPD_SRC_IN	Keeps the source pixels that cover the destination pixels and discards the remaining source and destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>Sa \times Da</math></li> <li>Result color value = <math>Sc \times Da</math></li> </ul>
vivPD_DST_IN	Keeps the destination pixels that cover source pixels and discards the remaining source and destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>Sa \times Da</math></li> <li>Result color value = <math>Sa \times Dc</math></li> </ul>
vivPD_SRC_OUT	Keeps the source pixels that do not cover destination pixels and discards the remaining source and destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>Sa \times (1 - Da)</math></li> <li>Result color value = <math>Sc \times (1 - Da)</math></li> </ul>

## 2 Data structures

Enumeration value	Description
vivPD_DST_OUT	Keeps the destination pixels that are not covered by source pixels and discards the remaining source and destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>D_a \times (1 - S_a)</math></li> <li>Result color value = <math>D_c \times (1 - S_a)</math></li> </ul>
vivPD_SRC_ATOP	Discards the source pixels that do not cover destination pixels and draws the remaining source pixels over destination pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>D_a</math></li> <li>Result color value = <math>S_c \times D_a + (1 - S_a) \times D_c</math></li> </ul>
vivPD_DST_ATOP	Discards the destination pixels that are not covered by source pixels and draws the remaining destination pixels over source pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>S_a</math></li> <li>Result color value = <math>S_a \times D_c + S_c \times (1 - D_a)</math></li> </ul>
vivPD_XOR	Discards the source and destination pixels where source pixels cover destination pixels and draws the remaining source pixels. <ul style="list-style-type: none"> <li>Result alpha value = <math>S_a + D_a - 2 \times S_a \times D_a</math></li> <li>Result color value = <math>S_c \times (1 - D_a) + (1 - S_a) \times D_c</math></li> </ul>

### 2.3.13 viv\_pool\_type

Specifies the memory allocation strategy.

Enumeration Value	Description
gcvPOOL_CONTIGUOUS	Allocates contiguous memory. If no contiguous memory is available, the allocation fails.
gcvPOOL_DEFAULT	Tries to allocate contiguous memory. If no contiguous memory is available, the system allocates memory with discrete pages.
gcvPOOL_USER	Uses user-reserved memory.

### 2.3.14 viv\_display\_size\_type

Specifies the display resolution and refresh rate.

Enumeration value	Description
vivDISPLAY_320_480_60	320 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_480_800_60	480 x 800 resolution at a refresh rate of 60 Hz
vivDISPLAY_480_864_60	480 x 864 resolution at a refresh rate of 60 Hz
vivDISPLAY_640_480_60	640 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_720_480_60	720 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_800_480_60	800 x 480 resolution at a refresh rate of 60 Hz
vivDISPLAY_1024_600_60	1024 x 600 resolution at a refresh rate of 60 Hz
vivDISPLAY_1024_768_60	1024 x 768 resolution at a refresh rate of 60 Hz
vivDISPLAY_1280_720_60	1280 x 720 resolution at a refresh rate of 60 Hz
vivDISPLAY_1920_1080_60	1920 x 1080 resolution at a refresh rate of 60 Hz

## 2 Data structures

Enumeration value	Description
vivDISPLAY_3840_2160_30	3840 x 2160 resolution at a refresh rate of 30 Hz
vivDISPLAY_3840_2160_60	3840 x 2160 resolution at a refresh rate of 60 Hz
vivDISPLAY_4096_2160_60	4096 x 2160 resolution at a refresh rate of 60 Hz
vivDISPLAY_5760_756_60	5760 x 756 resolution at a refresh rate of 60 Hz
vivDISPLAY_CUSTOMIZED	Custom resolution

### 2.3.15 viv\_display

Specifies the display panel.

Enumeration value	Description
vivDISPLAY_0	The display0 panel
vivDISPLAY_1	The display1 panel

### 2.3.16 viv\_dc\_features

Specifies the feature for [viv\\_dc\\_query\\_feature\(\)](#) to query.

Enumeration value	Description	Support (Yes/No/Value)
vivFEATURE_DISPLAY_COUNT	The number of supported panels	1
vivFEATURE_LAYER_COUNT	The total number of supported overlay layers and video/graphic layers	3
vivFEATURE_CURSOR_COUNT	The number of supported cursor layers	1
vivFEATURE_GAMMA_BIT_OUT	The number of output bits of the display gamma module	8
vivFEATURE_SECURITY	The secure mode, Trusted Execution Environment (TEE)	No
vivFEATURE_MMU	The memory management unit (MMU)	No
vivFEATURE_CURSOR_VERSION	The cursor version <ul style="list-style-type: none"> <li>The value 0 indicates that only the cursor size 32 x 32 in pixels is supported.</li> <li>Value 1 indicates that the cursor sizes 32 x 32 and 64 x 64 in pixels are supported.</li> </ul>	1
vivFEATURE_CSC_MOUDLE	The programmable color space conversion (CSC) matrix	No
vivFEATURE_3D_LUT	The 3D lookup table (LUT) feature	No
vivFEATURE_DE_GAMMA	The degamma feature	No
vivFEATURE_DP	Display Port feature	No
vivFEATURE_DP_YUV	Display Port with YUV feature	No
vivFEATURE_DBI	The Display Bus Interface (DBI) output	Yes
vivFEATURE_DPI	The Display Parallel Interface (DPI) output	Yes
vivFEATURE_NEW_GAMMA	The new gamma feature	No
vivFEATURE_COLOR_BAR	The color bar	No
vivFEATURE_CRC	The cyclic redundancy check (CRC) feature	No



## 2 Data structures

Enumeration value	Description	Support (Yes/No/Value)
vivFEATURE_40BIT_ADDRESS	The 40-bit address space	No
vivFEATURE_WRITEBACK	The write-back feature	No
vivFEATURE_PROGRAM_WB	Program Write Back buffer	No
vivFEATURE_CUSTOMER_TILE4X4	Custom tile alignment	Yes
vivFEATURE_DUAL_OS	The dual-OS feature.	No

### 2.3.17 viv\_dc\_layer\_cap

Specifies the feature for [viv\\_layer\\_query\\_capability\(\)](#) to query. Only vivLAYER\_CAP\_TILED is supported.

Enumeration Value	Description
vivLAYER_CAP_DEC400_DECOMPRESSION	The DEC400 decompression feature
vivLAYER_CAP_SCALE	The filtering feature for scaling and sharpness
vivLAYER_CAP_TILED	The tiling feature
vivLAYER_CAP_ROTATION	The full rotation feature
vivLAYER_CAP_ROI	The region of interest (ROI) feature

## 2.4 Structures

### 2.4.1 viv\_dc\_buffer

The structure to configure the buffer for a layer to access.

Member	Type	Description
handle[3]	<a href="#">gctPOINTER</a>	(Optional) The handle of the buffer memory, obtained from the <a href="#">viv_alloc_buffer()</a> API.
logical[3]	<a href="#">gctPOINTER</a>	(Optional) A pointer to the CPU logical address of the buffer, obtained from the <a href="#">viv_alloc_buffer()</a> API.
phyAddress[3]	<a href="#">gctUINT64</a>	The physical addresses of the buffer.
gpuAddress[3]	<a href="#">gctUINT64</a>	(Optional) The DPU virtual addresses of the buffer, obtained from the <a href="#">viv_alloc_buffer()</a> API. This member is valid only for display controllers with MMU. To query the support for MMU, call <a href="#">viv_dc_query_feature()</a> with vivFEATURE_MMU.
format	<a href="#">viv_input_format_type</a>	The color format of the layer input. This parameter is valid only for overlay layers and video/graphic layers. For cursor layers, use the format member in the <a href="#">viv_cursor</a> structure instead.

## 2 Data structures

Member	Type	Description
security	<a href="#">gctBOOL</a>	<p>(Optional) Specifies whether to enable the secure mode for the buffer. The available values include:</p> <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables the secure mode.</li> <li><a href="#">vivFALSE</a>: Disables the secure mode.</li> </ul> <p>Set this member to the same value as the security parameter in the <a href="#">viv_alloc_buffer()</a> API.</p> <p>This member is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the secure mode and MMU, call <a href="#">viv_dc_query_feature()</a> with <a href="#">vivFEATURE_SECURITY</a> and <a href="#">vivFEATURE_MMU</a> separately.</p>
pool	<a href="#">viv_pool_type</a>	<p>(Optional) The memory allocation strategy.</p> <p>Set this member to the same value as the Pool parameter in the <a href="#">viv_alloc_buffer()</a> API.</p>
tiling	<a href="#">viv_tiling_type</a>	The tiling type of the layer input.
width	<a href="#">gctUINT32</a>	The width of the layer input.
height	<a href="#">gctUINT32</a>	The height of the layer input.
stride[3]	<a href="#">gctUINT32</a>	The stride of each plane.

### See also

[3.2.1 viv\\_alloc\\_buffer\(\)](#)

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

[3.4.3 viv\\_layer\\_set\(\)](#)

### 2.4.2 3.5.2 [viv\\_set\\_cursor\(\)](#)[viv\\_tilestatus\\_buffer](#)

The structure to configure the tile status buffer for a layer.

Member	Type	Description
tileStatusHandle[3]	<a href="#">gctPOINTER</a>	(Optional) The handle of the buffer memory, obtained from the <a href="#">viv_alloc_buffer()</a> API.
tileStatusLogical[3]	<a href="#">gctPOINTER</a>	(Optional) A pointer to the CPU logical address of the buffer, obtained from the <a href="#">viv_alloc_buffer()</a> API.
tileStatusHWAddress[3]	<a href="#">gctUINT64</a>	The physical addresses of the buffer.
tileStatusGPUAddress[3]	<a href="#">gctUINT64</a>	<p>(Optional)</p> <p>This member is valid only for display controllers with MMU. Not Supported</p>
format	<a href="#">viv_input_format_type</a>	(Optional) The color format of the layer input.
security	<a href="#">gctBOOL</a>	<p>(Optional) This member is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the secure mode and MMU. Not Supported</p>
pool	<a href="#">viv_pool_type</a>	(Optional) The memory allocation strategy.

## 2 Data structures

Member	Type	Description
		Set this member to the same value as the Pool parameter in the <a href="#">viv_alloc_buffer()</a> API.
tiling	<a href="#">viv_tiling_type</a>	(Optional) The tiling type of the layer input.
width	<a href="#">gctUINT32</a>	(Optional) The width of the layer input.
height	<a href="#">gctUINT32</a>	(Optional) The height of the layer input.

### See also

[3.2.1 viv\\_alloc\\_buffer\(\)](#)

### 2.4.3 viv\_cursor

The structure of a cursor.

Member	Type	Description
hsx	<a href="#">gctUINT32</a>	The X offset, in pixels, of the top-left point to the hotspot.
hsy	<a href="#">gctUINT32</a>	The Y offset, in pixels, of the top-left point to the hotspot.
x	<a href="#">gctUINT32</a>	The X coordinate, in pixels, of the hotspot.
y	<a href="#">gctUINT32</a>	The Y coordinate, in pixels, of the hotspot.
size	Not supported ( <a href="#">viv_write_back_type</a> )	The size of the cursor.
bg_color	<a href="#">gctUINT</a>	The background color in the specified format.
fg_color	<a href="#">gctUINT</a>	The foreground color in the specified format.
format	<a href="#">viv_input_format_type</a>	The input color format of the cursor. Set this parameter to <code>vivCURSOR_ARGB</code> or leave it unspecified.

## 2 Data structures

### 2.4.4 viv\_layer\_alpha\_mode

The structure of the alpha value configurations.

Member	Type	Description
srcGlobalAlphaMode	<a href="#">viv_global_alpha_mode</a>	The type of alpha value to use for the source.
srcGlobalAlphaValue	<a href="#">gctUINT32</a>	The global alpha value for the source.
srcAlphaMode	<a href="#">viv_alpha_mode</a>	Specifies whether to reverse the source alpha value.
srcAlphaValue	<a href="#">gctUINT32</a>	Reserved.
dstGlobalAlphaMode	<a href="#">viv_global_alpha_mode</a>	The type of the alpha value to use for the destination.
dstGlobalAlphaValue	<a href="#">gctUINT32</a>	The global alpha value for the destination.
dstAlphaMode	<a href="#">viv_alpha_mode</a>	Specifies whether to reverse the destination alpha value.
dstAlphaValue	<a href="#">gctUINT32</a>	Reserved.

### 2.4.5 viv\_dc\_degamma

The structure of a degamma table.

Member	Type	Description
degammaTable[260][3]	<a href="#">gctUINT16</a>	<p>The degamma table with a size of 260 rows and 3 columns</p> <ul style="list-style-type: none"> <li>degammaTable[index][0]: The value for the red channel</li> <li>degammaTable[index][1]: The value for the green channel</li> <li>degammaTable[index][2]: The value for the blue channel</li> </ul> <p>where, <i>index</i> is a value in the range of [0, 259].</p>

### 2.4.6 viv\_dc\_gamma

The structure of a gamma table.

Member	Type	Description
gammaTable[260][3]	<a href="#">gctUINT16</a>	<p>The gamma table with a size of 260 rows and 3 columns</p> <ul style="list-style-type: none"> <li>gammaTable[index][0]: The value for the red channel</li> <li>gammaTable[index][1]: The value for the green channel</li> <li>gammaTable[index][2]: The value for the blue channel</li> </ul> <p>where <i>index</i> is a value in the range of [0, 259].</p>

### 2.4.7 viv\_output

Specifies the output interface type, color format and DPI-related attributes.

Member	Type	Description
type	<a href="#">viv_display_type</a>	The output interface type
format	<a href="#">viv_display_format_type</a>	The output color format

## 2 Data structures

### 2.4.8 viv\_dc\_rect

The structure of a rectangle.

Member	Type	Description
x	<a href="#">gctUINT32</a>	The X coordinate, in pixels, of the rectangle top-left point
y	<a href="#">gctUINT32</a>	The Y coordinate, in pixels, of the rectangle top-left point
w	<a href="#">gctUINT32</a>	The width, in pixels, of the rectangle
h	<a href="#">gctUINT32</a>	The height, in pixels, of the rectangle

### 2.4.9 viv\_dc\_color

The structure of an RGB color.

Member	Type	Description
a	<a href="#">gctUINT8</a>	The value of the alpha channel
r	<a href="#">gctUINT8</a>	The value of the red channel
g	<a href="#">gctUINT8</a>	The value of the green channel
b	<a href="#">gctUINT8</a>	The value of the blue channel

## 3 DPU APIs

### 3 DPU APIs

#### 3.1 Initialization

This section describes the APIs for display controller initialization, de-initialization, and reset.

##### 3.1.1 `viv_dc_init()`

###### Description

Starts the display controller and initializes platform-related functions.

Call this API before using the display controller hardware. Do not repeatedly call this API before `viv_dc_deinit()` is called.

###### Syntax

```
vivSTATUS viv_dc_init(  
    gctVOID  
);
```

###### Parameters

None.

###### Returns

`vivSTATUS`

###### See also

[3.1.2 `viv\_dc\_deinit\(\)`](#)

## 3 DPU APIs

### 3.1.2 viv\_dc\_deinit()

#### Description

Terminates the platform-related functions and stops the display controller.

Call this API after the application is completed. After this API is executed, call `viv_dc_init()` before any other DPU API.

#### Syntax

```
vivSTATUS viv_dc_deinit(  
    gctVOID  
);
```

#### Parameters

None.

#### Returns

`vivSTATUS`

#### See also

[3.1.1 viv\\_dc\\_init\(\)](#)

### 3.1.3 viv\_dc\_reset()

#### Description

Resets the display controller.

#### Syntax

```
vivSTATUS viv_dc_reset(  
    gctVOID  
);
```

#### Parameters

None.

#### Returns

`vivSTATUS`

## 3 DPU APIs

### 3.2 Buffer allocation

This section describes the APIs for buffer management.

#### 3.2.1 viv\_alloc\_buffer()

##### Description

Allocates system memory to a buffer.

##### Syntax

```
vivSTATUS viv_alloc_buffer(
    gctUINT32 Size,
    gctPOINTER *Handle,
    gctUINT32 *HardwareAddress,
    gctPOINTER *Logical,
    gctBOOL security,
    viv_pool_type Pool
);
```

##### Parameters

Parameter	Data type	Description
Size	<a href="#">gctUINT32</a>	The memory size, in bytes, to allocate. For viv_dc_buffer: <ul style="list-style-type: none"> <li>If the input data is in RGB format, the required memory size is: <math>\text{height} \times \text{width} \times \text{Number of bytes per pixel (Bpp)}</math></li> <li>If the input data is in YUV format, the required memory size is the sum of the result of the above formula for each plane.</li> </ul> For viv_tilestatus_buffer, the recommended memory size is: Memory size of viv_dc_buffer/128
Handle	<a href="#">gctPOINTER</a> *	An output parameter that serves as the handle of the allocated memory.
HardwareAddress	<a href="#">gctUINT32</a> *	An output parameter that indicates the physical address of the memory buffer.
Logical	<a href="#">gctPOINTER</a> *	An output parameter that indicates the current CPU logical address of the memory buffer.
security	<a href="#">gctBOOL</a>	Specifies whether to enable the secure mode for the memory buffer. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li>vivTRUE: Enables the secure mode. If the secure mode is enabled for the buffer, enable the secure mode for the layer with viv_cursor_security() or viv_layer_security() to ensure successful access from the layer to the buffer.</li> <li>vivFALSE: Disables the secure mode.</li> </ul> This parameter is valid only if the display controller is configured with MMU and supports the secure mode. To query the support for the



## 3 DPU APIs

Parameter	Data type	Description
		secure mode and MMU, call <code>viv_dc_query_feature()</code> with <code>vivFEATURE_SECURITY</code> and <code>vivFEATURE_MMU</code> separately.
Pool	<a href="#">viv_pool_type</a>	The memory allocation strategy. Set this parameter to <code>gcvPOOL_CONTIGUOUS</code> or <code>gcvPOOL_DEFAULT</code> . The value must be the same as that you set in the <code>viv_dc_buffer</code> or <code>viv_tilestatus_buffer</code> object.

### Returns

[vivSTATUS](#)

### See also

[2.4.1 viv\\_dc\\_buffer](#)

[2.4.2 viv\\_tilestatus\\_buffer](#)

[3.2.2 viv\\_free\\_buffer\(\)](#)

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

[3.5.3 viv\\_cursor\\_security\(\)](#)

## 3.2.2 viv\_free\_buffer()

### Description

Frees the buffer memory allocated with `viv_alloc_buffer()`.

### Syntax

```
vivSTATUS viv_free_buffer(
    gctPOINTER handle
);
```

### Parameters

Parameter	Data type	Description
handle	<a href="#">gctPOINTER</a>	The handle of the buffer memory to free.

### Returns

[vivSTATUS](#)

### See also

[3.2.1 viv\\_alloc\\_buffer\(\)](#)

## 3 DPU APIs

### 3.3 Capability query

This section describes the APIs you can use to query the feature support of the display controller and each layer.

#### 3.3.1 `viv_query_chipinfo()`

##### Description

Queries the list of features that the display controller supports. The order of the listed features follows that in the `viv_dc_features` structure, where the first feature is `vivFEATURE_DISPLAY_COUNT`.

##### Syntax

```
vivSTATUS viv_query_chipinfo (  
    gctBOOL *Features  
);
```

##### Parameters

Parameter	Data type	Description
Features	<a href="#">gctBOOL</a> *	A pointer to the feature list.

##### Returns

[vivSTATUS](#)

##### See also

[2.3.16 viv\\_dc\\_features](#)

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

## 3 DPU APIs

### 3.3.2 viv\_dc\_query\_feature()

#### Description

Queries whether the display controller supports a specified feature. Before you call this API, use the `viv_query_chipinfo()` API to obtain the list of supported features.

To query the write-back support, use this API with `vivFEATURE_WRITEBACK` and the `viv_display_query_capability()` API with `vivDISPLAY_CAP_PROGRAM_WB` separately.

#### Syntax

```
vivSTATUS viv_dc_query_feature(
    viv_dc_features feature
    gctUINT* value
);
```

#### Parameters

Parameter	Data type	Description
feature	<a href="#">viv_dc_features</a>	The feature to query.
value	<a href="#">gctUINT</a> *	<p>The return value.</p> <ul style="list-style-type: none"> <li>If the queried feature is <code>vivFEATURE_DISPLAY_COUNT</code>, <code>vivFEATURE_LAYER_COUNT</code>, or <code>vivFEATURE_CURSOR_COUNT</code>, the return value indicates the number of panels or layers.</li> <li>If the queried feature is <code>vivFEATURE_CURSOR_VERSION</code>: <ul style="list-style-type: none"> <li>The value 1 indicates that the cursor sizes 32 x 32 and 64 x 64 in pixels are supported.</li> <li>The value 0 indicates that only the cursor size 32 x 32 in pixels is supported.</li> </ul> </li> <li>For other features: <ul style="list-style-type: none"> <li>The value 1 indicates that the queried feature is supported.</li> <li>The value 0 indicates that the queried feature is not supported.</li> </ul> </li> </ul>

#### Returns

[vivSTATUS](#)

#### See also

[3.3.1 viv\\_query\\_chipinfo\(\)](#)

## 3 DPU APIs

### 3.3.3 viv\_layer\_query\_capability()

#### Description

Queries whether a layer supports a specified feature.

#### Syntax

```
vivSTATUS viv_layer_query_capability(
    gctUINT layer_id,
    viv_dc_layer_cap cap
    gctUINT* value
);
```

#### Parameters

Parameter	Data type	Description
layer_id	<a href="#">gctUINT</a>	The ID of the layer to query. For the ID of each layer, see Section 3.4.1, <a href="#">viv_dc_select_layer()</a> .
Cap	<a href="#">viv_dc_layer_cap</a>	The feature to query.
value	<a href="#">gctUINT</a> *	The return value. The possible values include: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: The queried feature is supported.</li> <li><a href="#">vivFALSE</a>: The queried feature is not supported.</li> </ul>

#### Returns

[vivSTATUS](#)

## 3.4 Overlay and video/graphic layers

This section describes the APIs you can use to configure the overlay and video/graphic layers. For the support of overlay and video/graphic layers by each display controller, see Section 3.4.1, [viv\\_dc\\_select\\_layer\(\)](#).

### 3.4.1 viv\_dc\_select\_layer()

#### Description

Selects an overlay or video/graphic layer by ID. The ID of each layer for different display controller hardware revisions is listed in the following table.

Hardware revision	Software-hardware layer mapping
DC8000Nano 5_5_4_rc3d	Software: {0, 1, 2} Hardware: {video0, overlay0, overlay1}

Before configuring an overlay or video/graphic layer, call this API to switch to the layer.

#### Syntax

```
vivSTATUS viv_dc_select_layer (
    gctUINT layerId
);
```

## 3 DPU APIs

### Parameters

Parameter	Data type	Description
layerId	<a href="#">gctUINT</a>	The ID of the layer to select.

### Returns

[vivSTATUS](#)

## 3.4.2 viv\_layer\_enable()

### Description

Enables or disables the selected overlay or video/graphic layer.

### Syntax

```
vivSTATUS viv_layer_enable (
    gctBOOL enable
);
```

### Parameters

Parameter	Data type	Description
Enable	<a href="#">gctBOOL</a>	Specifies whether to enable the layer. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables the layer.</li> <li><a href="#">vivFALSE</a>: Disables the layer.</li> </ul>

### Returns

[vivSTATUS](#)

### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

## 3 DPU APIs

### 3.4.3 viv\_layer\_set()

#### Description

Assigns a buffer to the selected overlay or video/graphic layer.

Before you call this API, make sure that the buffer memory is available. To use system memory, call `viv_alloc_buffer()` for memory allocation.

#### Syntax

```
vivSTATUS viv_layer_set(  
    viv_dc_buffer *buffer  
);
```

#### Parameters

Parameter	Data type	Description
buffer	<a href="#">viv_dc_buffer</a> *	A pointer to the buffer.

#### Returns

[vivSTATUS](#)

#### See also

[3.2.1 viv\\_alloc\\_buffer\(\)](#)

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

## 3 DPU APIs

### 3.4.4 viv\_layer\_zorder()

#### Description

Configures the z-order for the selected overly or video/graphic layer in a blending or color keying operation. For the blending and color keying description, see the Vivante hardware features document specific to the DPU hardware version.

#### Syntax

```
vivSTATUS viv_layer_zorder(  
    gctUINT8 zorder  
);
```

#### Parameters

Parameter	Data type	Description
zorder	<a href="#">gctUINT8</a>	<p>The z-order of the layer.</p> <p>The value 0 indicates the bottom layer sitting above the background layer. Other numbers index the ordering of the front layers.</p> <p>The default background color is RGB(0, 0, 0). To change the background color, use the <a href="#">viv_layer_set_background()</a> API.</p>

#### Returns

[vivSTATUS](#)

#### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

[3.5.1 viv\\_layer\\_set\\_background\(\)](#)

## 3 DPU APIs

### 3.4.5 viv\_layer\_set\_position()

#### Description

Sets the start coordinates for the selected overlay or video/graphic layer to display on a panel.

#### Syntax

```
vivSTATUS viv_layer_set_position(
    gctUINT    x,
    gctUINT    y
);
```

#### Parameters

Parameter	Data type	Description
x	<a href="#">gctUINT</a>	The X coordinate of the start point for the layer.
y	<a href="#">gctUINT</a>	The Y coordinate of the start point for the layer.

#### Returns

[vivSTATUS](#)

#### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)



### 3 DPU APIs

#### 3.4.6 viv\_layer\_colorkey()

##### Description

Configures the color keying feature for the selected overlay or video/graphic layer.

##### Syntax

```
vivSTATUS viv_layer_colorkey(  
    viv_dc_color *colorkey,  
    viv_dc_color *colorkeyHigh,  
    gctBOOL transparency  
);
```

##### Parameters

Parameter	Data type	Description
colorkey	<a href="#">viv_dc_color</a> *	A pointer to the low color value of the range to key out.
colorkeyHigh	<a href="#">viv_dc_color</a> *	A pointer to the high color value of the range to key out.
transparency	<a href="#">gctBOOL</a>	Specifies whether to enable transparency of the matching range at the layer. Set this parameter to one of the following values: <ul style="list-style-type: none"><li><a href="#">vivTRUE</a>: Enables transparency</li><li><a href="#">vivFALSE</a>: Disables transparency</li></ul>

##### Returns

[vivSTATUS](#)

##### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

## 3 DPU APIs

### 3.4.7 viv\_layer\_clear()

#### Description

Configures the clear feature for the selected overlay or video/graphic layer.

If the clear feature is enabled for the layer, the system takes the clear color as the source data of the layer and does not read data from the buffer of the layer.

If the layer clear feature is disabled and the DEC400 fast clear feature is enabled, the clear color is used as the DEC400 fast clear color. The system determines whether DEC400 fast clear is enabled based on the compression information in the buffer specified with the viv\_layer\_decompress() API.

#### Syntax

```
vivSTATUS viv_layer_clear(  
    viv_dc_color *clearColor,  
    gctBOOL enable  
);
```

#### Parameters

Parameter	Data type	Description
clearColor	<a href="#">viv_dc_color</a> *	A pointer to the clear color.
enable	<a href="#">gctBOOL</a>	Specifies whether to enable the clear feature for the layer. Set this parameter to one of the following values: <ul style="list-style-type: none"><li><a href="#">vivTRUE</a>: Enables the clear feature.</li><li><a href="#">vivFALSE</a>: Disables the clear feature.</li></ul>

#### Returns

[vivSTATUS](#)

#### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

### 3 DPU APIs

#### 3.4.8 viv\_set\_alpha()

##### Description

Configures the source and destination alpha values for the selected overlay or video/graphic layer.

##### Syntax

```
vivSTATUS viv_set_alpha(
    viv_layer_alpha_mode *Alpha
);
```

##### Parameters

Parameter	Data type	Description
Alpha	<a href="#">viv_layer_alpha_mode</a> *	A pointer to the alpha value configurations of the layer.

##### Returns

[vivSTATUS](#)

##### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

[3.4.9 viv\\_layer\\_poterduff\\_blend\(\)](#)

#### 3.4.9 viv\_layer\_poterduff\_blend()

##### Description

Enables or disables alpha blending for the selected overlay or video/graphic layer.

##### Syntax

```
vivSTATUS viv_layer_poterduff_blend(
    gctBOOL enable,
    viv_porter_duff_mode Mode
);
```

##### Parameters

Parameter	Data type	Description
Enable	<a href="#">gctBOOL</a>	Specifies whether to enable alpha blending. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables alpha blending.</li> <li><a href="#">vivFALSE</a>: Disables alpha blending.</li> </ul>
Mode	<a href="#">viv_porter_duff_mode</a>	The Porter-Duff blend mode.

## 3 DPU APIs

### Returns

[vivSTATUS](#)

### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

[3.4.8 viv\\_set\\_alpha\(\)](#)

### 3.4.10 viv\_layer\_set\_watermark()

#### Description

Sets the watermark value for the selected overlay or video/graphic layer.

#### Syntax

```
vivSTATUS viv_layer_set_watermark(
    gctUINT32    watermark
);
```

#### Parameters

Parameter	Data type	Description
watermark	<a href="#">gctUINT32</a>	The watermark value.

### Returns

[vivSTATUS](#)

### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

[3.4.11 viv\\_dc\\_set\\_qos\(\)](#)

### 3.4.11 viv\_dc\_set\_qos()

#### Description

Sets the DPU QoS values for all overlay layers and video/graphic layers.

#### Syntax

```
vivSTATUS viv_dc_set_qos(
    gctUINT32    low,
    gctUINT32    high
);
```

### 3 DPU APIs

#### Parameters

Parameter	Data type	Description
low	<a href="#">gctUINT32</a>	The QoS low value.
high	<a href="#">gctUINT32</a>	The QoS high value.

#### Returns

[vivSTATUS](#)

#### See also

[3.4.10 viv\\_layer\\_set\\_watermark\(\)](#)

### 3.4.12 viv\_layer\_set\_display()

#### Description

Selects the display panel for the selected overlay or video/graphic layer.

#### Syntax

```
vivSTATUS viv_layer_set_display(  
    viv_display    display  
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.

#### Returns

[vivSTATUS](#)

#### See also

[3.4.1 viv\\_dc\\_select\\_layer\(\)](#)

[3.4.2 viv\\_layer\\_enable\(\)](#)

## 3.5 Background and cursor layers

This section describes the APIs you can use to configure background layers and cursor layers.

DC8000Nano supports only one background layer and one cursor layer.

### 3.5.1 viv\_layer\_set\_background()

#### Description

Sets the background color for a display panel. The panel shows the background color in a region only if the color bar is disabled for the region.

## 3 DPU APIs

### Syntax

```
vivSTATUS viv_layer_set_background(
    viv_display    display,
    viv_dc_color   *bgColor
);
```

### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
bgColor	<a href="#">viv_dc_color</a> *	A pointer to the background color, which is default to RGB(0,0,0).

### Returns

[vivSTATUS](#)

## 3.5.2 viv\_set\_cursor()

### Description

Enables or disables the cursor layer for a display panel.

Before you call this API, make sure that a [viv\\_dc\\_buffer](#) object is configured for the layer. If you want the buffer to use system memory, call [viv\\_alloc\\_buffer\(\)](#) for memory allocation.

### Syntax

```
vivSTATUS viv_set_cursor(
    viv_display    display,
    viv_dc_buffer  *buffer,
    viv_cursor     *cursor,
    gctBOOL        enable
);
```

### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel whose cursor layer you want to configure.  <i>Note:</i> <i>The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.</i>
buffer	<a href="#">viv_dc_buffer</a> *	A pointer to the buffer of the cursor layer.
cursor	<a href="#">viv_cursor</a> *	A pointer to the cursor.
enable	<a href="#">gctBOOL</a>	Specifies whether to enable the cursor layer. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables the cursor layer.</li> <li><a href="#">vivFALSE</a>: Disables the cursor layer.</li> </ul>

### 3 DPU APIs

#### Returns

[vivSTATUS](#)

#### See also

[3.2.1 viv\\_alloc\\_buffer\(\)](#)

[3.5.3 viv\\_cursor\\_security\(\)](#)

[3.5.4 viv\\_cursor\\_offset\(\)](#)

[3.5.5 viv\\_cursor\\_move\(\)](#)

### 3.5.3 viv\_cursor\_security()

#### Description

Enables or disables the cursor layer in secure mode for a display panel.

This API is valid only for DC8200 that supports the secure mode. Before using this API, call [viv\\_dc\\_query\\_feature\(\)](#) with [vivFEATURE\\_SECURITY](#) to check whether the secure mode is supported.

*Note:* Calling this API overwrites the setting of the enable parameter in [viv\\_set\\_cursor\(\)](#).

#### Syntax

```
vivSTATUS viv_cursor_security(
    viv_display display,
    gctBOOL enable
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel whose cursor layer you want to configure.  <i>Note:</i> The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.
enable	<a href="#">gctBOOL</a>	Specifies whether to enable the cursor layer. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables the cursor layer.</li> <li><a href="#">vivFALSE</a>: Disables the cursor layer.</li> </ul>

#### Returns

[vivSTATUS](#)

## 3 DPU APIs

### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

[3.5.2 viv\\_set\\_cursor\(\)](#)

### 3.5.4 viv\_cursor\_offset()

#### Description

Sets the offset of the cursor top-left point to the hotspot. The top-left point refers to the upper-left corner of the cursor bounding box.

Make sure that the hotspot is located within the cursor image. To query the supported cursor sizes, call `viv_dc_query_feature()` with `vivFEATURE_CURSOR_VERSION`.

#### Syntax

```
vivSTATUS viv_cursor_hotspot(  
    viv_display display,  
    gctUINT32 hsx,  
    gctUINT32 hsy  
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel whose cursor layer you want to configure.  <i>Note:</i> <i>The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.</i>
hsx	<a href="#">gctUINT32</a>	The X offset, in pixels, of the top-left point to the hotspot.
hsy	<a href="#">gctUINT32</a>	The Y offset, in pixels, of the top-left point to the hotspot.

#### Returns

[vivSTATUS](#)

### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

[3.5.2 viv\\_set\\_cursor\(\)](#)



## 3 DPU APIs

### 3.5.5 viv\_cursor\_move()

#### Description

Sets a new position for the cursor hotspot on the same display panel.

#### Syntax

```
vivSTATUS viv_cursor_move(  
    viv_display display,  
    gctUINT32 x,  
    gctUINT32 y  
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel whose cursor layer you want to configure.  <i>Note: The cursor of the display0 panel is cursor0. The cursor of the display1 panel is cursor1.</i>
x	<a href="#">gctUINT32</a>	The new position X coordinate, in pixels, of the cursor hotspot.
y	<a href="#">gctUINT32</a>	The new position Y coordinate, in pixels, of the cursor hotspot.

#### Returns

[vivSTATUS](#)

#### See also

[3.5.2 viv\\_set\\_cursor\(\)](#)

## 3 DPU APIs

### 3.6 Post-processing for display

This section describes the APIs for post-processing configurations.

#### 3.6.1 `viv_gamma_enable()`

##### Description

Enables or disables the gamma feature for a display panel.

##### Syntax

```
vivSTATUS viv_gamma_enable(  
    viv_display display,  
    gctBOOL    enable  
);
```

##### Parameters

Parameter	Data type	Description
Display	<a href="#">viv_display</a>	The ID of the display panel.
enable	<a href="#">gctBOOL</a>	Specifies whether to enable the gamma feature. Set this parameter to one of the following values: <ul style="list-style-type: none"><li><code>vivTRUE</code>: Enables the feature.</li><li><code>vivFALSE</code>: Disables the feature.</li></ul>

##### Returns

[vivSTATUS](#)

##### See also

[3.6.2 `viv\_gamma\_init\(\)`](#)

[3.6.3 `viv\_set\_gamma\(\)`](#)

## 3 DPU APIs

### 3.6.2 viv\_gamma\_init()

#### Description

Initializes the gamma table.

#### Syntax

```
vivSTATUS viv_gamma_init(  
    viv_dc_gamma *gamma,  
    gctFLOAT gamma_value,  
    viv_dc_curve_type curve_type  
);
```

#### Parameters

Parameter	Data type	Description
gamma	<a href="#">viv_dc_gamma</a> *	A pointer to the gamma table.
gamma_value	<a href="#">gctFLOAT</a>	The index of the gamma function. This parameter is valid only if curve_type is set to VIV_DC_CURVE_GAMMA.

#### Returns

[vivSTATUS](#)

#### See also

[3.6.1 viv\\_gamma\\_enable\(\)](#)

[3.6.3 viv\\_set\\_gamma\(\)](#)

## 3 DPU APIs

### 3.6.3 viv\_set\_gamma()

#### Description

Sets a row in a gamma table for a display panel.

Before you use this API, make sure that the table of the gamma feature is available. To initiate the table, use the `viv_gamma_init()` API.

#### Syntax

```
vivSTATUS viv_set_gamma(  
    viv_display display,  
    gctUINT32 index,  
    gctUINT16 r,  
    gctUINT16 g,  
    gctUINT16 b  
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
index	<a href="#">gctUINT32</a>	The index of the row in the gamma table.
r	<a href="#">gctUINT16</a>	The gamma correction value for the red channel.
g	<a href="#">gctUINT16</a>	The gamma correction value for the green channel.
b	<a href="#">gctUINT16</a>	The gamma correction value for the blue channel.

#### Returns

[vivSTATUS](#)

#### See also

[3.6.1 viv\\_gamma\\_enable\(\)](#)

[3.6.2 viv\\_gamma\\_init\(\)](#)

## 3 DPU APIs

### 3.6.4 viv\_set\_dither()

#### Description

Enables or disables the dithering feature for a display panel.

#### Syntax

```
vivSTATUS viv_set_dither(
    viv_display display,
    gctBOOL enable
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
enable	<a href="#">gctBOOL</a>	Specifies whether to enable the dithering feature. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables dithering.</li> <li><a href="#">vivFALSE</a>: Disables dithering.</li> </ul>

#### Returns

[vivSTATUS](#)

## 3 DPU APIs

### 3.7 Display output

This section describes the APIs you can use to configure display output on panels.

Before configuring display output, call [viv\\_dc\\_query\\_feature\(\)](#) with `vivFEATURE_DISPLAY_COUNT` to query the number of panels supported by the display controller. The current number of supported panels is 1.

#### 3.7.1 `viv_set_display_size()`

##### Description

Sets the display resolution and refresh rate of a display panel.

##### Syntax

```
vivSTATUS viv_set_display_size(  
    viv_display    display,  
    viv_display_size_type type  
);
```

##### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
type	<a href="#">viv_display_size_type</a>	The display resolution and refresh rate of the display panel.

##### Returns

[vivSTATUS](#)

##### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

## 3 DPU APIs

### 3.7.2 viv\_set\_custom\_display\_size()

#### Description

Sets the custom display resolution and refresh rate of a display panel.

#### Syntax

```
vivSTATUS viv_set_custom_display_size(
    viv_display    display,
    gctUINT        hactive,
    gctUINT        hsync_start,
    gctUINT        hsync_end,
    gctUINT        htotal,
    gctUINT        vactive,
    gctUINT        vsync_start,
    gctUINT        vsync_end,
    gctUINT        vtotal
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
hactive	<a href="#">gctUINT</a>	The active resolution in the horizontal direction.
hsync_start	<a href="#">gctUINT</a>	The synchronization start of the horizontal direction, which is calculated as follows: $\text{hsync\_start} = \text{hactive} + \text{h\_front\_porch}$ Where h_front_porch indicates the front porch of horizontal synchronization signals.
hsync_end	<a href="#">gctUINT</a>	The synchronization end of horizontal direction, which is calculated as follows: $\text{hsync\_end} = \text{hsync\_start} + \text{h\_sync\_length}$ Where h_sync_length indicates the width of horizontal synchronization signals.
htotal	<a href="#">gctUINT</a>	The total resolution in the horizontal direction, which is calculated as follows: $\text{htotal} = \text{hsync\_end} + \text{h\_back\_porch}$ Where h_back_porch indicates the back porch of horizontal synchronization signals.
vactive	<a href="#">gctUINT</a>	The active resolution in the vertical direction.
vsync_start	<a href="#">gctUINT</a>	The synchronization start of vertical direction, which is calculated as follows: $\text{vsync\_start} = \text{vactive} + \text{v\_front\_porch}$ Where v_front_porch indicates the front porch of vertical synchronization signals.
vsync_end	<a href="#">gctUINT</a>	The synchronization end of vertical direction, which is calculated as follows: $\text{vsync\_end} = \text{vsync\_start} + \text{v\_sync\_length}$ Where v_sync_length indicates the width of vertical synchronization signals.
vtotal	<a href="#">gctUINT</a>	The total resolution of vertical direction, which is calculated as follows: $\text{vtotal} = \text{vsync\_end} + \text{v\_back\_porch}$

### 3 DPU APIs

Parameter	Data type	Description
		Where v_back_porch indicates the back porch of vertical synchronization signals.

#### Returns

[vivSTATUS](#)

#### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

### 3.7.3 viv\_set\_output()

#### Description

Enables or disables the output of a display panel and sets the output format.

If the Display Bus Interface (DBI) is selected as the output interface, call [viv\\_reset\\_dbi\(\)](#) to reset it to the idle state.

#### Syntax

```
vivSTATUS viv_set_output(
    viv_display    display,
    viv_output     *output,
    gctBOOL        enable
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
output	<a href="#">viv_output</a> *	A pointer to the output configurations.
enable	<a href="#">gctBOOL</a>	Specifies whether to enable the output for the display panel. Set this parameter to one of the following values: <ul style="list-style-type: none"> <li><a href="#">vivTRUE</a>: Enables the output. Pixels are displayed on the display panel through the specified output interface.</li> <li><a href="#">vivFALSE</a>: Disables the output. All pixels are black. This allows a display panel to have correct timing without pixel display.</li> </ul>

#### Returns

[vivSTATUS](#)

#### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

[3.7.4 viv\\_reset\\_dbi\(\)](#)



## 3 DPU APIs

### 3.7.4 viv\_reset\_dbi()

#### Description

Resets the Display Bus Interface (DBI) to the idle state. Call this API if the DBI is selected as the output interface by using viv\_set\_output().

#### Syntax

```
vivSTATUS viv_reset_dbi(
    gctVOID
);
```

#### Parameters

None.

#### Returns

[vivSTATUS](#)

#### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

[3.7.2 viv\\_set\\_output\(\)](#)

### 3.7.5 viv\_set\_output\_dbi()

#### Description

Enables or disables DBI output and sets the DBI type for a display panel.

.

#### Syntax

```
vivSTATUS viv_set_output_dbi(
    viv_display    display,
    viv_dbi_type    type
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel.
type	<a href="#">viv_dbi_type</a>	The DBI type.

#### Returns

[vivSTATUS](#)

## 3 DPU APIs

### See also

[3.3.2 viv\\_dc\\_query\\_feature\(\)](#)

## 3.8 Display controller access and debugging

This section describes the APIs that you can use to commit configurations and for debugging.

### 3.8.1 viv\_set\_commit()

#### Description

Commits the configurations to shadow registers and triggers display panels.

*Note:* The shadow registers pass the configurations to the counterpart registers at the next frame. To check whether a frame is finished, use the `viv_get_vblank_count()` API.

#### Syntax

```
vivSTATUS viv_set_commit(  
    gctUINT32    display_mask  
);
```

#### Parameters

Parameter	Data type	Description
display_mask	<a href="#">gctUINT32</a>	Specifies the display panels to trigger. Set this parameter to one of the following values: <ul style="list-style-type: none"><li>1: Triggers display0.</li><li>2: Triggers display1.</li><li>3: Triggers both display0 and display1.</li></ul>

#### Returns

[vivSTATUS](#)

### See also

[3.8.2 viv\\_get\\_vblank\\_count\(\)](#)

## 3 DPU APIs

### 3.8.2 viv\_get\_vblank\_count()

#### Description

Queries the number of interrupts caused. An interrupt is generated once a DC frame is finished.

You can use this API to check whether frames are finished. For details, see Section 4, [Programming with DPU APIs](#).

#### Syntax

```
vivSTATUS viv_get_vblank_count(
    viv_display display,
    gctUINT32 *count
);
```

#### Parameters

Parameter	Data type	Description
display	<a href="#">viv_display</a>	The ID of the display panel
count	<a href="#">gctUINT32</a> *	An output parameter that indicates the number of interrupts

#### Returns

[vivSTATUS](#)

## 4 Programming with DPU APIs

### 4 Programming with DPU APIs

The general procedure of programming with DPU APIs is as follows:

1. Start the display controller device with the [viv\\_dc\\_init\(\)](#) API.
2. Reset the display controller with the [viv\\_dc\\_reset\(\)](#) API.
3. Query the list of features supported by the hardware with the [viv\\_query\\_chipinfo\(\)](#) and [viv\\_dc\\_query\\_feature\(\)](#) APIs.
4. (Optional) Allocate buffers for layers with the [viv\\_alloc\\_buffer\(\)](#) API.

Skip this step if user-reserved memory is used.

5. Program the display controller by using the APIs described in the following sections:
  - Section 3.4, [Overlay and video/graphic layers](#)
  - Section 3.5, [Background and cursor layers](#)
  - Section 3.7, [Display output](#)
  - Section 3.6, [Post-processing for display](#)
6. Configure the hardware registers and trigger panels with the [viv\\_set\\_commit\(\)](#) API.

The configurations take effect after the current frame.

7. Check whether the current frame finishes, based on the number of caused interrupts queried with the [viv\\_get\\_vblank\\_count\(\)](#) API.
8. After the frame is finished, disable the layers and the write-back feature that are enabled in Steps 5 and 7.

This ensures that the display controller no longer has read or write requests.

For the APIs to use, see Section 3.4.2, [viv\\_layer\\_enable\(\)](#), Section 3.5.2, [viv\\_set\\_cursor\(\)](#)

## 4 Programming with DPU APIs

### 4.1 Example 1: Displaying through DPI

This section provides an example of using the DPU API for image display through the DPI output interface. This example shows Layer 0 from (0,0) to (640,480) on the display0 panel with the output format vivD24. Layer 0 is fed with ARGB8888-formatted linear data in the size of 640x480.

For detailed description of the programming settings, see Chapter 2, [Data structures](#) and Chapter 3, [DPU APIs](#).

```
gctINT ret = 0;
gctUINT width = 640, height = 480, Bpp = 4, stride = 640*4, phyAddr = 0, vblank0 =
0,
vblank1 = 0;
void *logical = 0, *handle = 0;
viv_dc_buffer buffer = {0};
viv_dc_rect display_rect = {0};
viv_output display_output = {0};
/* open device */
ret = viv_dc_init();
if(ret)
    return ret;
/* reset DC */
viv_dc_reset();
/* select layer0 */
viv_dc_select_layer(0);
/* enable layer0 */
viv_layer_enable(vivTRUE);
/* alloc contiguous memory for the frame buffer of layer0 */
ret = viv_alloc_buffer(width*height*Bpp, &handle, &phyAddr, &logical, vivFALSE,
gcvPOOL_DEFAULT);
if(ret)
    return ret;
/* config the buffer's phyAddr/format/tilemode/bufferWidth/bufferHeight/stride to
kernel */
buffer.handle[0] = handle;
buffer.logical[0] = logical;
buffer.phyAddress[0] = phyAddr;
buffer.stride[0] = stride;
buffer.format = vivARGB8888;
buffer.tiling = vivLINEAR;
buffer.width = 640;
buffer.height = 480;
viv_layer_set(&buffer);
/* config display region on panel */
display_rect.x = 0;
display_rect.y = 0;
display_rect.w = 640;
display_rect.h = 480;
/* if display region is equal to layer0's bufferSize, don't do scale */
viv_layer_scale(&display_rect, vivFILTER_H3_V3);
/* config the start coordinates of layer0 display region */
```

## 4 Programming with DPU APIs

```
viv_layer_set_position(0, 0);
/* config layer's zorder number */
viv_layer_zorder(0);
/* config layer0 show on panel0 */
viv_layer_set_display(vivDISPLAY_0);
/* config panel0's resolution and timing */
viv_set_display_size(vivDISPLAY_0, vivDISPLAY_640_480_60);
/* config panel0's output type and format */
display_output.type = vivDPI;
display_output.format = vivD24;
viv_set_output(vivDISPLAY_0, &display_output, vivTRUE);
/* fill data to layer0's buffer */
memset(logical, 100, width*height*Bpp);
/* config register and trig panel0 */
viv_set_commit(0x1);
/* when vblank1 > vblank0 means one frame finished */
/* commit completes after the current frame is processed. */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* we need to disable layer or cursor we have enabled before */
viv_layer_enable(vivFALSE);
/* commit again to let layer0 disabled */
viv_set_commit(0x1);
/* commit completes after the current frame is processed. */
/* new config will take effect at next frame */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* free memory allocated for layer0 */
viv_free_buffer(buffer.handle[0]);
```

## 4 Programming with DPU APIs

### 4.2 Example 2: Displaying through DBI Type B

This section provides an example of using the DPU API for image display through the DBI Type B interface. This example shows Layer 0 from (0,0) to (320,480) on the display0 panel with the output format D8R8G8B8. Layer 0 is fed with ARGB8888-formatted linear data in the size of 320x480.

For detailed description of the programming settings, see Chapter 2, [Data structures](#) and Chapter 3, [DPU APIs](#).

```
gctINT ret = 0;
gctUINT width = 320, height = 480, Bpp = 4, stride = 320*4, phyAddr = 0, vblank0 =
0,
vblank1 = 0;
void *logical = 0, *handle = 0;
viv_dc_buffer buffer = {0};
viv_dc_rect display_rect = {0};
viv_output display_output = {0};
viv_dbi_type dbi_type = vivDBI_B;
/* open device */
ret = viv_dc_init();
if(ret)
    return ret;
/* reset DC */
viv_dc_reset();
/* select layer0 */
viv_dc_select_layer(0);
/* enable layer0 */
viv_layer_enable(vivTRUE);
/* alloc contiguous memory for the frame buffer of layer0 */
ret = viv_alloc_buffer(width*height*Bpp, &handle, &phyAddr, &logical, vivFALSE,
gcvPOOL_DEFAULT);
if(ret)
    return ret;
/* config the buffer's phyAddr/format/tilemode/bufferWidth/bufferHeight/stride to
kernel */
buffer.handle[0] = handle;
buffer.logical[0] = logical;
buffer.phyAddress[0] = phyAddr;
buffer.stride[0] = stride;
buffer.format = vivARGB8888;
buffer.tiling = vivLINEAR;
buffer.width = width;
buffer.height = height;
viv_layer_set(&buffer);
/* config display region on panel */
display_rect.x = 0;
display_rect.y = 0;
display_rect.w = width;
display_rect.h = height;
/* if display region is equal to layer0's bufferSize, don't do scale */
viv_layer_scale(&display_rect, vivFILTER_H3_V3);
```

## 4 Programming with DPU APIs

```

/* config the start coordinates of layer0 display region */
viv_layer_set_position(0, 0);
/* config layer's zorder number */
viv_layer_zorder(0);
/* config layer0 show on panel0 */
viv_layer_set_display(vivDISPLAY_0);
/* config panel0's resolution and timing */
viv_set_display_size(vivDISPLAY_0, vivDISPLAY_320_480_60);
/* config panel0's output type and format */
display_output.type = vivDBI;
display_output.format = vivD8R8G8B8;
viv_set_output(vivDISPLAY_0, &display_output, vivTRUE);
viv_reset_dbi();
viv_set_output_dbi(dbi_type);
/* fill data to layer0's buffer */
memset(logical, 100, width*height*Bpp);
/* config register and trig panel0 */
viv_set_commit(0x1);
/* when vblank1 > vblank0 means one frame finished */
/* commit completes after the current frame is processed. */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* we need to disable layer or cursor we have enabled before */
viv_layer_enable(vivFALSE);
/* commit again to let layer0 disabled */
viv_set_commit(0x1);
/* commit completes after the current frame is processed. */
/* new config will take effect at next frame */
viv_get_vblank_count(vivDISPLAY_0, &vblank0);
do{
    usleep(10000);
    viv_get_vblank_count(vivDISPLAY_0, &vblank1);
}while(vblank0 == vblank1);
/* free memory allocated for layer0 */
viv_free_buffer(buffer.handle[0]);

```



## 5 List of Unsupported DPU APIs

This section lists unsupported functions corresponding to the list of unsupported features for DCNano8000 hardware. These functions and their structures are removed from this documentation. Their implementation is available within the code but is currently not supported by the current hardware.

- `viv_map_buffer`
- `viv_unmap_buffer`
- `viv_layer_security`
- `viv_layer_rotation`
- `viv_layer_cache_mode`
- `viv_layer_roi_enable`
- `viv_layer_roi_rect`
- `viv_layer_set_y2r`
- `viv_layer_degamma_enable`
- `viv_layer_degamma_init`
- `viv_layer_set_degamma`
- `viv_layer_set_r2r`
- `viv_layer_get_status`
- `viv_dc_request`
- `viv_set_color_bar`
- `viv_set_3d_lut`
- `viv_set_3d_lut_enlarge`
- `viv_set_output_csc`
- `viv_set_dest`
- `viv_set_writeback_dither`

## Revision history

### Revision history

Document revision	Date	Description of changes
*A	2025-09-24	Release to web.

#### Trademarks

All referenced product or service names and trademarks are the property of their respective owners.

**Edition 2025-09-24**

**Published by**

**Infineon Technologies AG**

**81726 Munich, Germany**

**© 2025 Infineon Technologies AG.  
All Rights Reserved.**

**Do you have a question about this document?**

**Email:**

[erratum@infineon.com](mailto:erratum@infineon.com)

**Document reference**

**002-40807 Rev. \*A**

#### Important notice

The information given in this document shall in no event be regarded as a guarantee of conditions or characteristics ("Beschaffheitsgarantie").

With respect to any examples, hints or any typical values stated herein and/or any information regarding the application of the product, Infineon Technologies hereby disclaims any and all warranties and liabilities of any kind, including without limitation warranties of non-infringement of intellectual property rights of any third party.

In addition, any information given in this document is subject to customer's compliance with its obligations stated in this document and any applicable legal requirements, norms and standards concerning customer's products and any use of the product of Infineon Technologies in customer's applications.

The data contained in this document is exclusively intended for technically trained staff. It is the responsibility of customer's technical departments to evaluate the suitability of the product for the intended application and the completeness of the product information given in this document with respect to such application.

#### Warnings

Due to technical requirements products may contain dangerous substances. For information on the types in question please contact your nearest Infineon Technologies office.

Except as otherwise explicitly approved by Infineon Technologies in a written document signed by authorized representatives of Infineon Technologies, Infineon Technologies' products may not be used in any applications where a failure of the product or any consequences of the use thereof can reasonably be expected to result in personal injury.